



# Autodesk® FMDesktop™ 2009

Autodesk®

## Facility Web Installation Guide

Customer and Administration Building, Ditzingen, Germany - Design by Barkow Leibinger Architects

# Table of Contents

---

<b>1 Introduction</b> .....	<b>3</b>
What is Facility Web? .....	3
How Does it Work? .....	3
<b>2 Hardware and Software Requirements</b> .....	<b>4</b>
<b>3 Installing Facility Web</b> .....	<b>6</b>
<b>4 Uninstalling Facility Web</b> .....	<b>8</b>
<b>5 Starting Facility Web</b> .....	<b>9</b>
<b>6 Linking to the FMDesktop Database</b> .....	<b>10</b>

# 1 Introduction

## *What is Facility Web?*

Facility Web is part of a computer-aided facility management suite of products called Autodesk® FMDesktop. Using this web-based facility management tool, you can distribute facility drawings, data, and reports across your corporate network or the Internet without any complicated software installations. Use the Facility Web Publishing Wizard to publish facility drawings and data directly to the Internet or your corporate intranet. Use the published Facility Web site and your web browser to view facility drawings and data.

Facility Web uses a simple point-and-click interface to provide a number of drawing-related functions, including panning, zooming, printing, and layering functions. It brings facility information to the desktops of facility managers using web technologies.

## *How Does it Work?*

Facility Web works with these components that perform different functions, but must be used together to make the program work:

- **FMDesktop Database** - The database component of the FMDesktop application suite. It is used to store the data records that are linked to your drawings.
- **Facility Manager Resource Folders** – The shared object storage component of the FMDesktop application suite. The folders are used to store the drawings, graphics, and documents associated with your facility data.

## 2 Hardware and Software Requirements

### Facility Web Publishing Wizard

The following requirements are in addition to any Microsoft® operating system requirements:

CATEGORY	REQUIREMENT
<b>Equipment:</b>	Personal computer with 500-MHz Intel® Pentium® III processor or faster VGA or higher-resolution monitor (1024 x 768 True Color) CD-ROM Mouse
<b>Operating System:</b>	<ul style="list-style-type: none"><li>• Microsoft® Windows® 2000 SP4</li><li>• Microsoft® Windows® XP Professional SP2</li><li>• Microsoft® Windows® Vista™ Enterprise</li><li>• Microsoft® Windows® Vista™ Business</li><li>• Microsoft® Windows® Vista™ Ultimate</li><li>• Microsoft® Windows® Vista™ Home Premium</li><li>• Microsoft® Windows® Server 2003</li></ul> Windows scripting host
<b>Computer Memory:</b>	512 MB RAM
<b>Hard Disk Space:</b>	550 MB free disk space for installation

## Facility Web Client

The following requirements are in addition to any Microsoft requirements for their various operating systems and any Autodesk requirements for your specific version of Autodesk® Design Review (ADR).

### Equipment

Personal computer with 800-MHz Pentium processor or faster  
VGA or higher-resolution monitor (1024 x 768, True Color)  
CD-ROM  
Mouse

### Operating System

- Microsoft® Windows® 2000 SP4
- Microsoft® Windows® Server 2003 (requires ADR 2008 or higher only)
- Microsoft® Windows® XP Home
- Microsoft® Windows® XP Professional SP2
- Microsoft® Windows® Vista™ Enterprise
- Microsoft® Windows® Vista™ Business
- Microsoft® Windows® Vista™ Ultimate
- Microsoft® Windows® Vista™ Home Premium

Native ADR 2008 or higher required

### RAM

512 MB

### Hard Disk Space

550 MB free disk space for installation

### Browser

Microsoft® Internet Explorer 6, Microsoft® Internet Explorer 7

**Note:** Browser security settings must allow cookies and the display of active content, and the popup blocker must be turned off for Facility Web pages.

## 3 Installing Facility Web

**Note:** You must have a Facility Web Publishing Wizard user's license for every computer on which you install the program. If you have questions about Facility Web licensing, contact FMDesktop Sales at [fmdesktopsales@autodesk.com](mailto:fmdesktopsales@autodesk.com).

**Important:** You must have full administrative privileges to install Facility Web.

1. Close any programs you have open on your computer. (This includes any programs that start automatically when you turn on your computer, such as virus scanners, task schedulers, toolbars, RealPlayer™, HotSync® Manager).
2. Put the Facility Web CD in your CD-ROM drive; your computer should automatically start the Facility Web setup program and open the Install Wizard. If not:
  - Click the Windows Start button in the bottom left corner of the screen.
  - Click Run.
  - Enter **D:\setup.exe** in the Open: field (where D:\ is your CD-ROM drive).
  - Click OK.
3. Click Read the Documentation on the Facility Web Install Wizard, review the available documentation to become familiar with the Facility Web application and installation requirements.
4. Click Install Products on the Facility Web Install Wizard, to begin the install process.
5. On the Select Products to Install screen you have the option of installing Autodesk® Design Review 2009 in addition to Facility Web. If you wish to install Autodesk Design Review 2009 on your machine, click the Autodesk Design Review 2009 check box so that a checkmark is displayed. Click Next.
6. After reading and accepting the Facility Web End User License Agreement, click I Accept, and then click Next.
7. It is recommended that you accept the default installation directory (C:\Program Files\FMDesktop\Facility Web 2009). If you wish to change the default installation location for Facility Web:
  - a. Click Configure.
  - b. Click Browse, and navigate to the location where you would like Facility Web installed.
  - c. Click OK to save the installation path.

- d. Click Next to complete the configuration.
  - e. Click Configuration Complete to return to the main installer screen.
8. To accept the displayed settings and begin installation, click Install.
  9. When the Facility Web installation has been completed successfully, click Finish.

## 4 Uninstalling Facility Web

Use the Add/Remove Programs tool on the Windows Control Panel to remove Facility Web from your computer. The listed name of the program is Autodesk Facility Web 2009.

## 5 Starting Facility Web

After successfully installing Facility Web, a launch icon displays on your desktop and on your Windows Start menu. To start the Facility Web Publishing Wizard, click the Facility Web Publishing Wizard icon on your desktop, or navigate to Autodesk > FMDesktop 2009 > Facility Web 2009 Publishing Wizard on your Windows Start menu.

## 6 Linking to the FMDesktop Database

After successfully installing the Facility Web Publishing Wizard and launching the application, you can use the Browse button on the initial screen to locate and connect the program to an FMDesktop data source and to the FMDesktop resource folders.

By design, the Facility Web Publishing Wizard looks for the FMDesktop resource folders in the same folder where your data source file is stored. This means that when you connect the program to an FMDesktop data source, you are also connecting it to the location of your FMDesktop resource folders.

To connect the Facility Web Publishing Wizard to an FMDesktop data source:

1. Launch the Facility Web Publishing Wizard
2. On the initial Facility Web Publishing Wizard screen, click the Browse button.
3. Navigate to a valid FMDesktop 2009 data source, select it, and then click Open.

**Note:** Facility Web 2009 will only function when connected to a new FMDesktop 2009 data source or when connected to a data source from a previous version of FMDesktop that has been updated using Facility Manager 2009.